



There are a few steps to perform before you can download data from your unit. This document is to help guide you through until you become accustomed to use


Log in



Home screen



Turn your unit on (3-5 second long press until unit lights RED)



Your unit will stay red for 30seconds as it is powering up




After 30seconds the colour will change to an amber-orange colour, this indicates ready to download your data

If your unit flashes fast red as soon as turned on, indicates low power. In this case charge your unit before you carry on

With IOS it is important that you turn **off** the phones **WIFI assist** feature before you start, Then turn on your phones wifi if not already on

Step 1. Turn off WIFI assist


1. Go into setting and select mobile data



2. once in mobile data you then need to scroll down and turn off wifi assist (usually at the bottom)




3. slide the tab to turn off




Step 2. Ensure your WIFI is on

4. Slide your screen up and check your wifi on here



With IOS it is important that you turn **OFF** the phones mobile data **before** you start, this is because you will be using WIFI to download your session.

Step 3. Turn off Mobile DATA. Follow either of the options below




Turn off mobile data here


Slide screen up

Go into settings and follow these steps below


1



2



3



Slide tab to off position





You are now ready to capture the data from your Quantrax GPS unit

Select menu On the screen

Next select capture data

Next press **START DOWNLOAD**



Message is displayed




You need to go into settings

Follow these steps to ensure you are connected to your GPS units wifi Once you have connected you can then go back into the Quantrax app


1. select settings



2. Select the Wifi tab




3. Select your units Wifi



If this is the first time use, you may be asked for a password. The default password for your unit is: **12345678**




The code is on the back of your unit




Having selected settings you will be navigated to the screen displayed in step 1 above (1.)

Go back into the App and press Download
The download is dependent on the length of session the bar below displays the progress

Once completed you now need to connect to your mobile data or other wifi source




DO NOT
click on OK yet




When it comes to uploading your data quantrax is able to perform anywhere. You can use Wifi or Mobile data to upload and view your session by just following the below instructions


Go back into your phones settings you will see the Quantrax gps units wifi is still connected




You now need to select a local wifi to be able to upload your data



Or turn your mobile data back on




Make sure that you Allow access to the Quantrax App, Scroll down your apps




when you get to Quantrax if it is not on then slide the tab to on


Go back into the APP and click OK



Complete the session description and then select upload



Once your session has been processed you will receive a message



You will now be able to see the summary of your session



